

## 版本要求

1.1.4 (Windows Server 2012以下不支持)

## 下载链接


64  
位: [https://github.com/cloudbase/cloudbase-init/releases/download/1.1.4/CloudbaseInitSetup\\_1\\_1\\_4\\_x64.msi](https://github.com/cloudbase/cloudbase-init/releases/download/1.1.4/CloudbaseInitSetup_1_1_4_x64.msi)

32  
位: [https://github.com/cloudbase/cloudbase-init/releases/download/1.1.4/CloudbaseInitSetup\\_1\\_1\\_4\\_x86.msi](https://github.com/cloudbase/cloudbase-init/releases/download/1.1.4/CloudbaseInitSetup_1_1_4_x86.msi)

## 操作步骤

### 一、安装软件

1. 第一到第三步点next即可
2. 第四步



3. 第五步  
点install  
然后等待安装就行

4. 第六步  
Finish

### 二、修改配置文件

修改cloudbase-init.conf

文件地址 `C:\Program Files\Cloudbase Solutions\Cloudbase-Init\conf\cloudbase-init.conf`

\*\*内容:

```
metadata_services=cloudbaseinit.metadata.services.nocloudservice.NoCloudConfigDriveService
resizes_on_boot=true
plugins=cloudbaseinit.plugins.common.networkconfig.NetworkConfigPlugin,cloudbaseinit.plugins.c
ommon.sethostname.SetHostNamePlugin,cloudbaseinit.plugins.common.userdata.UserDataPlugin,cl
oudbaseinit.plugins.windows.extendvolumes.ExtendVolumesPlugin,cloudbaseinit.plugins.windows.lic
ensing.WindowsLicensingPlugin**
```



```
cloudbase-init.conf - 记事本
文件(F) 编辑(E) 格式(O) 查看(V) 帮助(H)
[DEFAULT]
username=Administrator
groups=Administrators|
inject_user_password=true
config_drive_raw_hhd=true
config_drive_cdrom=true
config_drive_vfat=true
bsdtar_path=C:\Program Files\Cloudbase Solutions\Cloudbase-Init\bin\bsdtar.exe
mtools_path=C:\Program Files\Cloudbase Solutions\Cloudbase-Init\bin\
verbose=true
debug=true
log_dir=C:\Program Files\Cloudbase Solutions\Cloudbase-Init\log\
log_file=cloudbase-init.log
default_log_levels=comtypes=INFO,suds=INFO,iso8601=WARN,requests=WARN
logging_serial_port_settings=
mtu_use_dhcp_config=true
ntp_use_dhcp_config=true
local_scripts_path=C:\Program Files\Cloudbase Solutions\Cloudbase-Init\LocalScripts\
check_latest_version=true
metadata_services=cloudbaseinit.metadata.services.nocloudservice.NoCloudConfigDriveService
resizes_on_boot=true
plugins=cloudbaseinit.plugins.common.networkconfig.NetworkConfigPlugin,cloudbaseinit.plugins.common.sethostname.SetHostNamePlugin,cloudbaseinit.plugins.common.userdata.UserDataPlugin,cloudbaseinit.plugins.windows.extendvolumes.ExtendVolumesPlugin,cloudbaseinit.plugins.windows.licensing.WindowsLicensingPlugin
```

plugins参数的值解释:

- NetworkConfigPlugin[]网卡设置
- SetHostNamePlugin[]设置主机名
- ExtendVolumesPlugin[]磁盘扩容
- UserDataPlugin[]用户数据注入
- WindowsLicensingPlugin[]激活window instance

### 三、修改网卡名称

外网网卡改成 Ethernet0

内网网卡改成 Ethernet1

组织 ▾

-  **Ethernet0**  
网络 2  
Intel(R) PRO/1000 MT Networ...
-  **Ethernet1**  
未识别的网络  
Intel(R) PRO/1000 MT Networ...